

XML Tag	Attributes	Parent Node	Comments	Value Required	I/O	Max Length*	Allowed Values
<Stations>			Root node for the entire xml document				
	count		Corresponds to the record count in the WL database table.		O		
<Station>		<Stations>	Contains the return header information				
	id		"Id" field in the "Clients" table	Y	I		
	NodeIndex		Reserved for WorldLink	Y	I		0
<Code>		<Station>	"Code" field. It defines the name of the computer on the network.	Y	I	20	
<SiteCode>		<Station>	It defines the site code is currently being used for processing shipments.	Y	O		
<SiteCity>		<Station>	It defines the site City is currently being used for processing shipments.	Y	I		
<PrintLabel>		<Station>	"PrintLabel" field. It defines the workstation to print out shipping labels.	Y	I		
<LabelPrinter>		<Station>	"LabelPrinterType" field. It defines the Label Printer.	Y	I		0-Eltron Printer 1-Datamax Printer 4-Sato Printer and Zebra Printer
<LabelPrinterType>		<Station>	It defines the Label printer drive which is available on the machine. Labels are printed out whenever a package is shipped	Y	I		
<ManifestPrinter >		<Station>	It defines the Manifest printer drive which is available on the machine.	Y	I		
	active		IF Printer is selected the then active is true either active false	Y	I		
<ManifestPrinterType>		<Station>	It defines the manifest printer drive which is available on the machine. Manifest are printed out whenever a package is shipped	Y	I		
<UseScale>		<Station>	"UseScale" field. It defines the workstation to communicate with a locally connected scale	Y	I		
<ScaleType>		<Station>	"ScaleType" field. It defines the scales that have been certified to operate with WorldLink.	Y	I		
<ScalePort>		<Station>	"ScalePort" field. It defines the workstation to accept input from a locally connected scanner.	Y	I		
<ScaleBaudRate>		<Station>	"ScaleBaudRate" field.	Y	I		



XML Tag	Attributes	Parent Node	Comments	Value Required	I/O	Max Length*	Allowed Values
<ScaleDataBit>		<Station>	"ScaleDataBits" field.	Y	I		
<ScaleParity>		<Station>	"ScaleParity" field.	Y	I		
<ScaleStopBit>		<Station>	"ScaleStopBits" field.	Y	I		
<SerialScanner>		<Station>		Y	I		
<SS_Port>		<Station>	"SS_Port" field.	Y	I		
<SS_BaudRate>		<Station>	"SS_BaudRate" field.	Y	I		
<SS_DataBit>		<Station>	"SS_DataBits" field.	Y	I		
<SS_Parity>		<Station>	"SS_Parity" field.	Y	I		
<SS_StopBit>		<Station>	"SS_StopBits" field.	Y	I		
<BOLPrinter>		<Station>	"PrintBOL" field. It defines the workstation to print a Bill of Lading (BOL).	Y	I		
	active		If print BOL selected then active set TRUE otherwise Active set FALSE.	Y	I		
<CIPrinter>		<Station>	"PrintCI" field. It defines the workstation to print a Commercial Invoice (CI). A Commercial Invoice will be printed out whenever an international package is shipped	Y	I		
	active		If printCI selected then active set TRUE otherwise Active set FALSE.	Y	I		
<SLIPrinter>		<Station>	"PrintSLI" field. It defines the workstation to print out a Shipper's Letter of Instructions (SLI).A SLI will be printed out whenever an international package is shipped or required by the company being shipped to.	Y	I		
	active		If SLIPrint selected then active set TRUE otherwise Active set FALSE.	Y	I		
<DGPrinter>		<Station>	"PrintDG" Field. It defines the workstation to print out the Dangerous Goods report.	Y	I		
	active		If DGPrinter selected then active set TRUE otherwise Active set FALSE.	Y	I		
<TNTDGPrinter>		<Station>	"PrintTNTDG" field. It defines the workstation to print out the Dangerous Goods report for TNT NL.	Y	I		
	active		IF TNTDGPrinter selected then active set TRUE otherwise Active set FALSE.	Y	I		



Heightening Shipping Efficiency for World Commerce

Copyright © 2009 CMS GlobalSoft, Inc. All rights are reserved

Date Published:3/26/2009 | Page 2 of 4

XML Tag	Attributes	Parent Node	Comments	Value Required	I/O	Max Length*	Allowed Values
<NAFTAPrinter>		<Station>	"PrintNAFTA" field. It defines the workstation to print out a NAFTA certificate. A NAFTA certificate will be printed out whenever an international package is shipped to Canada or Mexico.	Y	I		
	active		IF NAFTAPrinter selected then active set TRUE otherwise Active set FALSE.	Y	I		
<COPrinter>		<Station>	"PrintCO" field. It defines the workstation to print out a Certificate of Origin (CO). A CO will be printed out whenever an international package is shipped or required by the company being shipped to.	Y	I		
	active		IF COPrinter selected then active set TRUE otherwise Active set FALSE.	Y	I		
<SEDPrinter>		<Station>	"PrintSED" field. It defines the workstation to print out a Shipper's Export Declaration (SED). AN SED will be printed out whenever an international package is shipped and assigned to the organization.	Y	I		
	active		IF SEDPrinter selected then active set TRUE otherwise Active set FALSE.	Y	I		
<AutoPost>		<Station>	"AutoPostMode" field. It defines the workstation to automatically process a shipment that is retrieved from an outside source (such as a database) and prepare itself for the next shipment.	Y	I		
<CustomShipPage>		<Station>	"UseCustomShipPage" Field. It defines the custom .asp pages are placed in customer folder. Based on customization, there will be one or more pages required in the customer folder. If there are no custom .asp pages, a 'Page cannot be found' error message will be displayed when the process shipment page is accessed.	Y	I		
	active		IF CustomShipPage is selected then active set TRUE otherwise Active set FALSE.	Y	I		



XML Tag	Attributes	Parent Node	Comments	Value Required	I/O	Max Length*	Allowed Values
<CustomViewPage>		<Station>	"UseCustomViewPage" Field. It define the custom .asp pages are placed in customer folder. Based on customization, there will be one or more pages required in the customer folder. If there are no custom .asp pages, a 'Page cannot be found' error message will be displayed when the process shipment page is accessed.	Y	I		
	active		IF CustomViewPage is selected then active set TRUE otherwise Active set FALSE.	Y	I		

